

StarWind Virtual SAN: Configuration Guide for Microsoft Hyper-V Server [Hyper-V], VSAN Deployed as a Controller VM (CVM) using PowerShell CLI

2024

TECHNICAL PAPERS



Trademarks

“StarWind”, “StarWind Software” and the StarWind and the StarWind Software logos are registered trademarks of StarWind Software. “StarWind LSFS” is a trademark of StarWind Software which may be registered in some jurisdictions. All other trademarks are owned by their respective owners.

Changes

The material in this document is for information only and is subject to change without notice. While reasonable efforts have been made in the preparation of this document to assure its accuracy, StarWind Software assumes no liability resulting from errors or omissions in this document, or from the use of the information contained herein. StarWind Software reserves the right to make changes in the product design without reservation and without notification to its users.

Technical Support and Services

If you have questions about installing or using this software, check this and other documents first - you will find answers to most of your questions on the [Technical Papers](#) webpage or in [StarWind Forum](#). If you need further assistance, please [contact us](#) .

About StarWind

StarWind is a pioneer in virtualization and a company that participated in the development of this technology from its earliest days. Now the company is among the leading vendors of software and hardware hyper-converged solutions. The company’s core product is the years-proven StarWind Virtual SAN, which allows SMB and ROBO to benefit from cost-efficient hyperconverged IT infrastructure. Having earned a reputation of reliability, StarWind created a hardware product line and is actively tapping into hyperconverged and storage appliances market. In 2016, Gartner named StarWind “Cool Vendor for Compute Platforms” following the success and popularity of StarWind HyperConverged Appliance. StarWind partners with world-known companies: Microsoft, VMware, Veeam, Intel, Dell, Mellanox, Citrix, Western Digital, etc.

Copyright ©2009-2018 StarWind Software Inc.

No part of this publication may be reproduced, stored in a retrieval system, or transmitted in any form or by any means, electronic, mechanical, photocopying, recording or otherwise, without the prior written consent of StarWind Software.

Annotation

Relevant Products

This guide applies to StarWind Virtual SAN and StarWind Virtual SAN Free (Version V8 (Build 15260, OVF Version 20230901) and earlier).

For newer versions of StarWind Virtual SAN (Version V8 (Build 15260, CVM Version 20231016) and later), please refer to this configuration guide: [StarWind Virtual SAN: Configuration Guide for Microsoft Hyper-V Server \[Hyper-V\], VSAN Deployed as a Controller Virtual Machine \(CVM\) using PowerShell CLI](#)

Purpose

The guide is to assist IT professionals and system administrators in the seamless deployment and configuration of Failover Cluster on Microsoft Windows Server with storage, provided by StarWind Virtual SAN CVM, while emphasizing adherence to best practices and system requirements.

Audience

This guide is designed for IT specialists, system administrators, and technical professionals aiming to deploy and configure Failover Cluster on Microsoft Windows Server with StarWind Virtual SAN CVM shared storage created with PowerShell CLI.

Expected Result

Upon completion of this guide, users will have gained a comprehensive understanding of the deployment and configuration process for Failover cluster on Microsoft Windows Server with StarWind CVM-based highly-available storage.

Introduction To Starwind Virtual San Cvm

StarWind Virtual SAN Controller Virtual Machine (CVM) comes as a prepackaged Linux Virtual Machine (VM) to be deployed on any industry-standard hypervisor. It creates a VM-centric and high-performing storage pool for a VM cluster.

This guide describes the deployment and configuration process of the StarWind Virtual SAN CVM.

Starwind Vsan System Requirements

Prior to installing StarWind Virtual SAN, please make sure that the system meets the requirements, which are available via the following link:

<https://www.starwindsoftware.com/system-requirements>

Recommended RAID settings for HDD and SSD disks:


<https://knowledgebase.starwindsoftware.com/guidance/recommended-raid-settings-for-hdd-and-ssd-disks/>

Please read StarWind Virtual SAN Best Practices document for additional information:

<https://www.starwindsoftware.com/resource-library/starwind-virtual-san-best-practices>

Pre-Configuring The Windows Server Hosts

The diagram below illustrates the network and storage configuration of the solution:



1. Make sure that a domain controller is configured and the servers are added to the


domain.

NOTE: Please follow the recommendation in [KB article](#) on how to place a DC in case of StarWind Virtual SAN usage.

2. Deploy Windows Server on each server and install Failover Clustering and Multipath I/O features, as well as the Hyper-V role on both servers. This can be done through Server Manager (Add Roles and Features menu item).

3. Define at least 2x network interfaces on each node that will be used for the Synchronization and iSCSI/StarWind heartbeat traffic. Do not use iSCSI/Heartbeat and Synchronization channels over the same physical link. Synchronization and iSCSI/Heartbeat links can be connected either via redundant switches or directly between the nodes (see diagram above).

4. Separate external Virtual Switches should be created for iSCSI and Synchronization traffic based on the selected before iSCSI and Synchronization interfaces. Using Hyper-V Manager open Virtual Switch Manager and create two external Virtual Switches: one for the iSCSI/StarWind Heartbeat channel (iSCSI) and another one for the Synchronization channel (Sync).



5. Configure and set the IP address on each virtual switch interface. In this document, the 172.16.10.x subnet is used for iSCSI/StarWind heartbeat traffic, while 172.16.20.x subnet is used for the Synchronization traffic.

NOTE: In case NIC supports SR-IOV, enable it for the best performance. An additional internal switch is required for iSCSI Connection. Contact support for additional details.

6. Set MTU size to 9000 on iSCSI and Sync interfaces using the following Powershell script.

```
$iSCSIs = (Get-NetAdapter -Name "*iSCSI*").Name
$SynCs = (Get-NetAdapter -Name "*Sync*").Name
foreach ($iSCSI in $iSCSIs) {
Set-NetAdapterAdvancedProperty -Name "$iSCSI" -RegistryKeyword
"*JumboPacket" -Registryvalue 9014
Get-NetAdapterAdvancedProperty -Name "$iSCSI" -RegistryKeyword
"*JumboPacket"
}
}
```

```
foreach ($Sync in $Syncs) {  
Set-NetAdapterAdvancedProperty -Name "$Sync" -RegistryKeyword  
"*JumboPacket" -Registryvalue 9014  
Get-NetAdapterAdvancedProperty -Name "$Sync" -RegistryKeyword  
"*JumboPacket"  
}
```

It will apply MTU 9000 to all iSCSI and Sync interfaces if they have iSCSI or Sync as part of their name.


NOTE: MTU setting should be applied on the adapters only if there is no live production running through the NICs.

Enabling Multipath Support

7. Open the MPIO Properties manager: Start -> Windows Administrative Tools -> MPIO. Alternatively, run the following PowerShell command :

```
mpioctl
```

8. In the Discover Multi-Paths tab, select the Add support for iSCSI devices checkbox and click Add.



9. When prompted to restart the server, click Yes to proceed.

10. Repeat the same procedure on the other server.


Installing File Server Roles

Please follow the steps below if file shares configuration is required

Scale-Out File Server (Sofs) For Application Data

1. Open Server Manager: Start -> Server Manager.
2. Select: Manage -> Add Roles and Features.
3. Follow the installation wizard steps to install the roles selected in the screenshot


below:



4. Restart the server after installation is completed and perform steps above on the each server.

File Server For General Use With Smb Share


1. Open Server Manager: Start -> Server Manager.
2. Select: Manage -> Add Roles and Features.
3. Follow the installation wizard steps to install the roles selected in the screenshot below:



4. Restart the server after installation is completed and perform steps above on each server.

File Server For General Use With Nfs Share


1. Open Server Manager: Start -> Server Manager.
2. Select: Manage -> Add Roles and Features.
3. Follow the installation wizard steps to install the roles selected in the screenshot below:



4. Restart the server after installation is completed and perform steps above on each server.


Deploying Starwind Virtual San Cvm

1. Download StarWind VSAN CVM to the Hyper-V server:
[VSAN by StarWind: Overview](#)
2. Extract the VM .vhdx file from the downloaded archive.
3. Open Hyper-V Manager and create a new Hyper-V VM.
4. Specify the name of the virtual machine with StarWind VSAN, and choose the location for the VM. For example: C:\SW1\




5. Copy .vhdx to the folder where the VM was created. In this case, its C:\ SW1\Virtual Hard Disks\


6. Choose Generation 2 VM.




7. Assign memory to the VM. We recommend allocating at least 8GB of RAM for StarWind CVM. If StarWind L1 cache is used, an appropriate amount of RAM should be assigned.




8. Choose the management network for the VM.




9. Connect .vhdx to the VM.




10. Review the Summary and click Finish to create the VM.




11. Right-click on the VM and choose Settings. Open Firmware and move the option Hard Drive to the first place in the list.




12. Go to the Security page and uncheck the Enable Secure Boot box.




13. Go to Memory and move the slider for Memory weight to High.




14. Go to Processor and assign 8 vCPUs to the VM.




15. Click Add Hardware and add NICs for iSCSI and Synchronization traffic to the VM.






16. Configure Automatic Start and Stop actions, so the VM will always start automatically.




17. Choose Shut down the guest operating system as an Automatic Stop Action.



18. Repeat all the steps from this section on other Windows Server hosts.
19. Start virtual machines on all Windows Server hosts.

Configuring Starwind Virtual San Vm Settings


1. Open the VM console and check the IP address received via DHCP (or which was assigned manually).



Another alternative is to log into the VM via console and assign static IP using nmcli if there is no DHCP,


2. Now, open the web browser and enter the IP address of the VM. Log into the VM using the following default credentials:

- username: user
- password: rds123RDS
- NOTE: Make sure to check the “Reuse my password for privileged tasks” box




3. After a successful login, click Accounts on the left sidebar.

4. Select a user and click Set Password.




5. On the left sidebar, click Networking.




Here, the Management IP address of the StarWind Virtual SAN Virtual Machine can be configured, as well as IP addresses for iSCSI and Synchronization networks. In case the Network interface is inactive, click on the interface, turn it on, and set it to Connect automatically.


6. Click on Automatic (DHCP) to set the IP address (DNS and gateway – for Management).



7. The result should look like in the picture below:



NOTE: It is recommended to set MTU to 9000 on interfaces dedicated for iSCSI and Synchronization traffic. Change Automatic to 9000, if required.



8. Alternatively, log into the VM via the VMware console and assign a static IP address by editing the configuration file of the interface located by the following path:
/etc/sysconfig/network-scripts


9. Open the file corresponding to the Management interface using a text editor, for example: `sudo nano /etc/sysconfig/network-scripts/ifcfg-eth0`

10. Edit the file:


- change the line `BOOTPROTO=dhcp` to: `BOOTPROTO=static`
- add the IP settings needed to the file:
- `IPADDR=192.168.12.10`
- `NETMASK=255.255.255.0`
- `GATEWAY=192.168.12.1`
- `DNS1=192.168.1.1`

11. Restart the interface using the following cmdlet: `sudo ifdown eth0, sudo ifup eth0`, or restart the VM.

12. Change the Host Name from the System tab by clicking on it:



13. Change System time and NTP settings if required:



14. Repeat the steps above on each StarWind VSAN VM.

Configuring Storage


StarWind Virtual SAN for vSphere can work on top of Hardware RAID or Linux Software RAID (MDADM) inside of the Virtual Machine.

Please select the required option:


Configuring Storage With Hardware Raid

1. Open VM Settings in Hyper-V and add drive to the VM, which going to be used by StarWind service. It is recommended to pass the entire RAID array to the VM by selecting a physical hard disk option.


NOTE: Using virtual hard disks is not recommended due to potential performance issues. Thick provisioned virtual disks should be used to improve storage performance.




2. Login to StarWind VSAN VM web console and access the Storage section. Locate the recently added disk in the Drives section and choose it.




3. The added disk does not have any partitions and filesystem. Press the Create Partition Table button to create the partition.



4. Press Create Partition to format the disk and set the mount point. The mount point should be as follows: /mnt/%yourdiskname%



5. On the Storage section, under Content, navigate to the Filesystem tab. Click Mount.



Configuring Starwind Management Console


1. Install StarWind Management Console on each server or on a separate workstation with Windows OS (Windows 7 or higher, Windows Server 2008 R2 and higher) using the installer available here.

NOTE: StarWind Management Console and PowerShell Management Library components are required.


2. Select the appropriate option to apply the StarWind License key.

Once the appropriate license key has been received, it should be applied to StarWind Virtual SAN service via Management Console or PowerShell.

3. Open StarWind Management Console and click Add Server.




4. Type the IP address of the StarWind Virtual SAN in the pop-up window and click OK.



5. Select the server and click Connect.

6. Click Apply Key... on the pop-up window.



7. Select Load license from file and click the Load button.

8. Select the appropriate license key.

As an alternative, PowerShell can be used. Open StarWind InstallLicense.ps1 script with PowerShell ISE as administrator. It can be found here:

C:\Program Files\StarWind

Software\StarWind\StarWindX\Samples\powershell\InstallLicense.ps1

Type the IP address of StarWind Virtual SAN VM and credentials of StarWind Virtual SAN service (defaults login: root, password: starwind).

Add the path to the license key.

```

Administrator: Windows PowerShell ISE
File Edit View Tools Debug Add-ons Help
InstallLicense.ps1 X
1 #
2 # The following example shows how to apply license on a server
3 #
4 Import-Module StarWindX
5
6 Enable-SWXLog
7
8 $server = New-SWServer -host 127.0.0.1 -port 3261 -user root -password starwind
9
10 try
11 {
12     $server.Connect()
13
14     Get-SWLicense $server
15
16     Remove-SWLicense $server
17
18     #apply license key
19     Set-SWLicense $server "C:\License\licensekey.swk"
20 }
21 catch
22 {
23     Write-Host $_ -foreground red
24 }
25 finally
26 {
27     $server.Disconnect()
28 }
29
PS C:\Program Files\StarWind Software\StarWind\StarWindX\Samples\powershell>
Ln 1 Col 1 | 100%

```

9. After the license key is applied, StarWind devices can be created.
NOTE: In order to manage StarWind Virtual SAN service (e.g. create ImageFile devices, VTL devices, etc.), StarWind Management Console can be used.

Creating Starwind Ha Luns Using Powershell

1. Open PowerShell ISE as Administrator.
2. Open StarWindX sample CreateHA_2.ps1 using PowerShell ISE. It can be found here: C:\Program Files\StarWind Software\StarWind\StarWindX\Samples\

```

1 param($addr="192.168.12.10", $port=3261, $user="root", $password="starwind",
2 $addr2="192.168.12.11", $port2=$port, $user2=$user, $password2=$password,
3
4 #common
5 $initMethod="Clear",
6 $size=2048,
7 $sectorSize=512,
8 $failover=0,
9 $bmpType=1,
10 $bmpStrategy=0,
11
12 #primary node
13 $imagePath="VSA Storage\mnt\crypted1",
14 $imageName="testha02",
15 $createImage=$true,
16 $storageName="",
17 $targetAlias="target02",
18 $autoSynch=$true,
19 $poolName="pool1",
20 $syncSessionCount=1,
21 $saluaOptimized=$true,
22 $cacheMode="none",
23 $cacheSize=0,
24 $syncInterface="#p2={0}:3260" -f "172.16.10.20",
25 $hbInterface="#p2=172.16.20:3260",
26 $createTarget=$true,
27 $bmpFolderPath=""
28
29 #secondary node
30 $imagePath2="VSA Storage\mnt\crypted1",
31 $imageName2="testha02",
32 $createImage2=$true,
33 $storageName2="",
34 $targetAlias2="target02",
35 $autoSynch2=$true,
36 $poolName2="pool1",
37 $syncSessionCount2=1,
38 $saluaOptimized2=$false,
39 $cacheMode2=$cacheMode,
40 $cacheSize2=$cacheSize,
41 $syncInterface2="#p1={0}:3260" -f "172.16.10.10",
42 $hbInterface2="#p1=172.16.10:3260",
43 $createTarget2=$true,
44 $bmpFolderPath2=""
45 )
46
47 Import-Module StarWindX
48
49 try
50 {
51     Enable-SwXLog -Level SW_LOG_LEVEL_DEBUG
52     $server = New-SWServer -host $addr -port $port -user $user -password $password
53     $server.Connect()
54 }
55 catch {
56     #Error handling
57 }
58
59 #-----
60
61 #-----
62
63 #-----
64
65 #-----
66
67 #-----
68
69 #-----
70
71 #-----
72
73 #-----
74
75 #-----
76
77 #-----
78
79 #-----
80
81 #-----
82
83 #-----
84
85 #-----
86
87 #-----
88
89 #-----
90
91 #-----
92
93 #-----
94
95 #-----
96
97 #-----
98
99 #-----
100
101 #-----
102
103 #-----
104
105 #-----
106
107 #-----
108
109 #-----
110
111 #-----
112
113 #-----
114
115 #-----
116
117 #-----
118
119 #-----
120
121 #-----
122
123 #-----
124
125 #-----
126
127 #-----
128
129 #-----
130
131 #-----
132
133 #-----
134
135 #-----
136
137 #-----
138
139 #-----
140
141 #-----
142
143 #-----
144
145 #-----
146
147 #-----
148
149 #-----
150
151 #-----
152
153 #-----
154
155 #-----
156
157 #-----
158
159 #-----
160
161 #-----
162
163 #-----
164
165 #-----
166
167 #-----
168
169 #-----
170
171 #-----
172
173 #-----
174
175 #-----
176
177 #-----
178
179 #-----
180
181 #-----
182
183 #-----
184
185 #-----
186
187 #-----
188
189 #-----
190
191 #-----
192
193 #-----
194
195 #-----
196
197 #-----
198
199 #-----
200
201 #-----
202
203 #-----
204
205 #-----
206
207 #-----
208
209 #-----
210
211 #-----
212
213 #-----
214
215 #-----
216
217 #-----
218
219 #-----
220
221 #-----
222
223 #-----
224
225 #-----
226
227 #-----
228
229 #-----
230
231 #-----
232
233 #-----
234
235 #-----
236
237 #-----
238
239 #-----
240
241 #-----
242
243 #-----
244
245 #-----
246
247 #-----
248
249 #-----
250
251 #-----
252
253 #-----
254
255 #-----
256
257 #-----
258
259 #-----
260
261 #-----
262
263 #-----
264
265 #-----
266
267 #-----
268
269 #-----
270
271 #-----
272
273 #-----
274
275 #-----
276
277 #-----
278
279 #-----
280
281 #-----
282
283 #-----
284
285 #-----
286
287 #-----
288
289 #-----
290
291 #-----
292
293 #-----
294
295 #-----
296
297 #-----
298
299 #-----
300
301 #-----
302
303 #-----
304
305 #-----
306
307 #-----
308
309 #-----
310
311 #-----
312
313 #-----
314
315 #-----
316
317 #-----
318
319 #-----
320
321 #-----
322
323 #-----
324
325 #-----
326
327 #-----
328
329 #-----
330
331 #-----
332
333 #-----
334
335 #-----
336
337 #-----
338
339 #-----
340
341 #-----
342
343 #-----
344
345 #-----
346
347 #-----
348
349 #-----
350
351 #-----
352
353 #-----
354
355 #-----
356
357 #-----
358
359 #-----
360
361 #-----
362
363 #-----
364
365 #-----
366
367 #-----
368
369 #-----
370
371 #-----
372
373 #-----
374
375 #-----
376
377 #-----
378
379 #-----
380
381 #-----
382
383 #-----
384
385 #-----
386
387 #-----
388
389 #-----
390
391 #-----
392
393 #-----
394
395 #-----
396
397 #-----
398
399 #-----
400
401 #-----
402
403 #-----
404
405 #-----
406
407 #-----
408
409 #-----
410
411 #-----
412
413 #-----
414
415 #-----
416
417 #-----
418
419 #-----
420
421 #-----
422
423 #-----
424
425 #-----
426
427 #-----
428
429 #-----
430
431 #-----
432
433 #-----
434
435 #-----
436
437 #-----
438
439 #-----
440
441 #-----
442
443 #-----
444
445 #-----
446
447 #-----
448
449 #-----
450
451 #-----
452
453 #-----
454
455 #-----
456
457 #-----
458
459 #-----
460
461 #-----
462
463 #-----
464
465 #-----
466
467 #-----
468
469 #-----
470
471 #-----
472
473 #-----
474
475 #-----
476
477 #-----
478
479 #-----
480
481 #-----
482
483 #-----
484
485 #-----
486
487 #-----
488
489 #-----
490
491 #-----
492
493 #-----
494
495 #-----
496
497 #-----
498
499 #-----
500
501 #-----
502
503 #-----
504
505 #-----
506
507 #-----
508
509 #-----
510
511 #-----
512
513 #-----
514
515 #-----
516
517 #-----
518
519 #-----
520
521 #-----
522
523 #-----
524
525 #-----
526
527 #-----
528
529 #-----
530
531 #-----
532
533 #-----
534
535 #-----
536
537 #-----
538
539 #-----
540
541 #-----
542
543 #-----
544
545 #-----
546
547 #-----
548
549 #-----
550
551 #-----
552
553 #-----
554
555 #-----
556
557 #-----
558
559 #-----
560
561 #-----
562
563 #-----
564
565 #-----
566
567 #-----
568
569 #-----
570
571 #-----
572
573 #-----
574
575 #-----
576
577 #-----
578
579 #-----
580
581 #-----
582
583 #-----
584
585 #-----
586
587 #-----
588
589 #-----
590
591 #-----
592
593 #-----
594
595 #-----
596
597 #-----
598
599 #-----
600
601 #-----
602
603 #-----
604
605 #-----
606
607 #-----
608
609 #-----
610
611 #-----
612
613 #-----
614
615 #-----
616
617 #-----
618
619 #-----
620
621 #-----
622
623 #-----
624
625 #-----
626
627 #-----
628
629 #-----
630
631 #-----
632
633 #-----
634
635 #-----
636
637 #-----
638
639 #-----
640
641 #-----
642
643 #-----
644
645 #-----
646
647 #-----
648
649 #-----
650
651 #-----
652
653 #-----
654
655 #-----
656
657 #-----
658
659 #-----
660
661 #-----
662
663 #-----
664
665 #-----
666
667 #-----
668
669 #-----
670
671 #-----
672
673 #-----
674
675 #-----
676
677 #-----
678
679 #-----
680
681 #-----
682
683 #-----
684
685 #-----
686
687 #-----
688
689 #-----
690
691 #-----
692
693 #-----
694
695 #-----
696
697 #-----
698
699 #-----
700
701 #-----
702
703 #-----
704
705 #-----
706
707 #-----
708
709 #-----
710
711 #-----
712
713 #-----
714
715 #-----
716
717 #-----
718
719 #-----
720
721 #-----
722
723 #-----
724
725 #-----
726
727 #-----
728
729 #-----
730
731 #-----
732
733 #-----
734
735 #-----
736
737 #-----
738
739 #-----
740
741 #-----
742
743 #-----
744
745 #-----
746
747 #-----
748
749 #-----
750
751 #-----
752
753 #-----
754
755 #-----
756
757 #-----
758
759 #-----
760
761 #-----
762
763 #-----
764
765 #-----
766
767 #-----
768
769 #-----
770
771 #-----
772
773 #-----
774
775 #-----
776
777 #-----
778
779 #-----
780
781 #-----
782
783 #-----
784
785 #-----
786
787 #-----
788
789 #-----
790
791 #-----
792
793 #-----
794
795 #-----
796
797 #-----
798
799 #-----
800
801 #-----
802
803 #-----
804
805 #-----
806
807 #-----
808
809 #-----
810
811 #-----
812
813 #-----
814
815 #-----
816
817 #-----
818
819 #-----
820
821 #-----
822
823 #-----
824
825 #-----
826
827 #-----
828
829 #-----
830
831 #-----
832
833 #-----
834
835 #-----
836
837 #-----
838
839 #-----
840
841 #-----
842
843 #-----
844
845 #-----
846
847 #-----
848
849 #-----
850
851 #-----
852
853 #-----
854
855 #-----
856
857 #-----
858
859 #-----
860
861 #-----
862
863 #-----
864
865 #-----
866
867 #-----
868
869 #-----
870
871 #-----
872
873 #-----
874
875 #-----
876
877 #-----
878
879 #-----
880
881 #-----
882
883 #-----
884
885 #-----
886
887 #-----
888
889 #-----
890
891 #-----
892
893 #-----
894
895 #-----
896
897 #-----
898
899 #-----
900
901 #-----
902
903 #-----
904
905 #-----
906
907 #-----
908
909 #-----
910
911 #-----
912
913 #-----
914
915 #-----
916
917 #-----
918
919 #-----
920
921 #-----
922
923 #-----
924
925 #-----
926
927 #-----
928
929 #-----
930
931 #-----
932
933 #-----
934
935 #-----
936
937 #-----
938
939 #-----
940
941 #-----
942
943 #-----
944
945 #-----
946
947 #-----
948
949 #-----
950
951 #-----
952
953 #-----
954
955 #-----
956
957 #-----
958
959 #-----
960
961 #-----
962
963 #-----
964
965 #-----
966
967 #-----
968
969 #-----
970
971 #-----
972
973 #-----
974
975 #-----
976
977 #-----
978
979 #-----
980
981 #-----
982
983 #-----
984
985 #-----
986
987 #-----
988
989 #-----
990
991 #-----
992
993 #-----
994
995 #-----
996
997 #-----
998
999 #-----
1000

```

2. Configure script parameters according to the following example:

```

param($addr="192.168.12.10", $port=3261, $user="root",
$password="starwind",
    $addr2="192.168.12.11", $port2=$port, $user2=$user,
$password2=$password,
#common
    $initMethod="Clear",
    $size=2048,
    $sectorSize=512,
    $failover=0,
    $bmpType=1,
    $bmpStrategy=0,
#primary node
    $imagePath="VSA Storage\mnt\crypted1",
    $imageName="testha02",
    $createImage=$true,
    $storageName="",
    $targetAlias="target02",
    $autoSynch=$true,

```



```

    $poolName="pool1",
    $syncSessionCount=1,
    $aluaOptimized=$true,
    $cacheMode="none",
    $cacheSize=0,
    $syncInterface="#p2={0}:3260" -f "172.16.20.20",
    $hbInterface="#p2={0}:3260" -f "172.16.10.20",
    $createTarget=$true,
    $bmpFolderPath="",
#secondary node
    $imagePath2="VSA Storage\mnt\crypted1",
    $imageName2="testha02",
    $createImage2=$true,
    $storageName2="",
    $targetAlias2="target02",
    $autoSynch2=$true,
    $poolName2="pool1",
    $syncSessionCount2=1,
    $aluaOptimized2=$false,
    $cacheMode2=$cacheMode,
    $cacheSize2=$cacheSize,
    $syncInterface2="#p1={0}:3260" -f "172.16.20.10",
    $hbInterface2="#p1={0}:3260" -f "172.16.10.10",
    $createTarget2=$true,
    $bmpFolderPath2=""
)
Import-Module StarWindX

try
{
    Enable-SWXLog -level SW_LOG_LEVEL_DEBUG

    $server = New-SWServer -host $addr -port $port -user
$user -password $password

    $server.Connect()

    $firstNode = new-Object Node

    $firstNode.HostName = $addr
    $firstNode.HostPort = $port
    $firstNode.Login = $user
    $firstNode.Password = $password
    $firstNode.ImagePath = $imagePath

```

```

$firstNode.ImageName = $imageName
$firstNode.Size = $size
$firstNode.CreateImage = $createImage
$firstNode.StorageName = $storageName
$firstNode.TargetAlias = $targetAlias
$firstNode.AutoSynch = $autoSynch
$firstNode.SyncInterface = $syncInterface
$firstNode.HBInterface = $hbInterface
$firstNode.PoolName = $poolName
$firstNode.SyncSessionCount = $syncSessionCount
$firstNode.ALUAOptimized = $aluaOptimized
$firstNode.CacheMode = $cacheMode
$firstNode.CacheSize = $cacheSize
$firstNode.FailoverStrategy = $failover
$firstNode.CreateTarget = $createTarget
$firstNode.BitmapStoreType = $bmpType
$firstNode.BitmapStrategy = $bmpStrategy
$firstNode.BitmapFolderPath = $bmpFolderPath
#
# device sector size. Possible values: 512 or 4096(May
be incompatible with some clients!) bytes.
#
$firstNode.SectorSize = $sectorSize
$secondNode = new-Object Node

$secondNode.HostName = $addr2
$secondNode.HostPort = $port2
$secondNode.Login = $user2
$secondNode.Password = $password2
$secondNode.ImagePath = $imagePath2
$secondNode.ImageName = $imageName2
$secondNode.CreateImage = $createImage2
$secondNode.StorageName = $storageName2
$secondNode.TargetAlias = $targetAlias2
$secondNode.AutoSynch = $autoSynch2
$secondNode.SyncInterface = $syncInterface2
$secondNode.HBInterface = $hbInterface2
$secondNode.SyncSessionCount = $syncSessionCount2
$secondNode.ALUAOptimized = $aluaOptimized2
$secondNode.CacheMode = $cacheMode2
$secondNode.CacheSize = $cacheSize2
$secondNode.FailoverStrategy = $failover
$secondNode.CreateTarget = $createTarget2
$secondNode.BitmapFolderPath = $bmpFolderPath2

```

```

        $device = Add-HADevice -server $server -firstNode
$firstNode -secondNode $secondNode -initMethod $initMethod
        while ($device.SyncStatus -ne
[SwHaSyncStatus]::SW_HA_SYNC_STATUS_SYNC)
        {
                $syncPercent =
$device.GetPropertyValue("ha_synch_percent")
                Write-Host "Synchronizing: $($syncPercent)%" -
foreground yellow

                Start-Sleep -m 2000

                $device.Refresh()
        }
}
catch
{
        Write-Host $_ -foreground red
}
finally
{
        $server.Disconnect()
}

```

Detailed explanation of script parameters:

-addr, -addr2 — partner nodes IP address.

Format: string. Default value: 192.168.0.1, 192.168.0.1

allowed values: localhost, IP-address

-port, -port2 — local and partner node port.

Format: string. Default value: 3261

-user, -user2 — local and partner node user name.

Format: string. Default value: root

-password, -password2 — local and partner node user password.

Format: string. Default value: starwind

#common

-initMethod -

Format: string. Default value: Clear

-size - set size for HA-devcie (MB)

Format: integer. Default value: 12

-sectorSize - set sector size for HA-device

Format: integer. Default value: 512

allowed values: 512, 4096

-failover – set type failover strategy
 Format: integer. Default value: 0 (Heartbeat)
 allowed values: 0, 1 (Node Majority)
 -bmpType – set bitmap type, is set for both partners at once
 Format: integer. Default value: 1 (RAM)
 allowed values: 1, 2 (DISK)
 -bmpStrategy – set journal strategy, is set for both partners at once
 Format: integer. Default value: 0
 allowed values: 0, 1 – Best Performance (Failure), 2 – Fast Recovery (Continuous)

#primary node

-imagePath – set path to store the device file
 Format: string. Default value: My computer\C\starwind”. For Linux the following format should be used: “VSA Storage\mnt\mount_point”
 -imageName – set name device
 Format: string. Default value: masterImg21
 -createImage – set create image file
 Format: boolean. Default value: true
 -targetAlias – set alias for target
 Format: string. Default value: targetha21
 -poolName – set storage pool
 Format: string. Default value: pool1
 -aluaOptimized – set Alua Optimized
 Format: boolean. Default value: true
 -cacheMode – set type L1 cache (optional parameter)
 Format: string. Default value: wb
 allowed values: none, wb, wt
 -cacheSize – set size for L1 cache in MB (optional parameter)
 Format: integer. Default value: 128
 allowed values: 1 and more
 -syncInterface – set sync channel IP-address from partner node
 Format: string. Default value: “#p2={0}:3260”
 -hbInterface – set heartbeat channel IP-address from partner node
 Format: string. Default value: “”
 -createTarget – set creating target
 Format: string. Default value: true
 Even if you do not specify the parameter -createTarget, the target will be created automatically.
 If the parameter is set as -createTarget \$false, then an attempt will be made to create the device with existing targets, the names of which are specified in the -targetAlias (targets must already be created)
 -bmpFolderPath – set path to save bitmap file
 Format: string.

```
#secondary node
-imagePath2 - set path to store the device file
Format: string. Default value: "My computer\C\starwind". For Linux the following format
should be used: "VSA Storage\mnt\mount_point"
-imageName2 - set name device
Format: string. Default value: masterImg21
-createImage2 - set create image file
Format: boolean. Default value: true
-targetAlias2 - set alias for targetFormat: string.
Default value: targetha22
-poolName2 - set storage pool
Format: string. Default value: pool1
-aluaOptimized2 - set Alua Optimized
Format: boolean. Default value: true
-cacheMode2 - set type L1 cache (optional parameter)
Format: string. Default value: wb
allowed values: wb, wt
-cacheSize2 - set size for L1 cache in MB (optional parameter)
Format: integer. Default value: 128
allowed values: 1 and more
-syncInterface2 - set sync channel IP-address from partner node
Format: string. Default value: "#p1={0}:3260"
-hbInterface2 - set heartbeat channel IP-address from partner node
Format: string. Default value: ""
-createTarget2 - set creating target
Format: string. Default value: true
Even if you do not specify the parameter -createTarget, the target will be created
automatically.If the parameter is set as -createTarget $false, then an attempt will be
made to create the device with existing targets, the names of which are specified in the -
targetAlias (targets must already be created)
-bmpFolderPath2 - set path to save bitmap file
Format: string.
```

Selecting The Failover Strategy

StarWind provides 2 options for configuring a failover strategy:

Heartbeat

The Heartbeat failover strategy allows avoiding the "split-brain" scenario when the HA cluster nodes are unable to synchronize but continue to accept write commands from the initiators independently. It can occur when all synchronization and heartbeat channels

disconnect simultaneously, and the partner nodes do not respond to the node's requests. As a result, StarWind service assumes the partner nodes to be offline and continues operations on a single-node mode using data written to it.

If at least one heartbeat link is online, StarWind services can communicate with each other via this link. The device with the lowest priority will be marked as not synchronized and get subsequently blocked for the further read and write operations until the synchronization channel resumption. At the same time, the partner device on the synchronized node flushes data from the cache to the disk to preserve data integrity in case the node goes down unexpectedly. It is recommended to assign more independent heartbeat channels during the replica creation to improve system stability and avoid the "split-brain" issue.

With the heartbeat failover strategy, the storage cluster will continue working with only one StarWind node available.

Node Majority

The Node Majority failover strategy ensures the synchronization connection without any additional heartbeat links. The failure-handling process occurs when the node has detected the absence of the connection with the partner.

The main requirement for keeping the node operational is an active connection with more than half of the HA device's nodes. Calculation of the available partners is based on their "votes".

In case of a two-node HA storage, all nodes will be disconnected if there is a problem on the node itself, or in communication between them. Therefore, the Node Majority failover strategy requires the addition of the third Witness node or file share (SMB) which participates in the nodes count for the majority, but neither contains data on it nor is involved in processing clients' requests. In case an HA device is replicated between 3 nodes, no Witness node is required.

With Node Majority failover strategy, failure of only one node can be tolerated. If two nodes fail, the third node will also become unavailable to clients' requests.


Please select the required option:

Provisioning Starwind Ha Storage To Windows Server Hosts


1. Launch Microsoft iSCSI Initiator: Start -> Windows Administrative Tools -> iSCSI Initiator. Alternatively, launch it using the command below in the command line interface:

```
iscsicpl
```


2. Navigate to the Discovery tab.



3. Click the Discover Portal button. The Discover Target Portal dialog appears. Type 172.16.10.10.




4. Click the Advanced button. Select Microsoft iSCSI Initiator as a Local adapter and select Initiator IP. Confirm the actions to complete the Target Portal discovery.




5. Click the Discover Portal... button once again.


6. In Discover Target Portal dialog, type in the iSCSI interface IP address of the partner node that will be used to connect the StarWind provisioned targets. Click Advanced.



7. Select Microsoft iSCSI Initiator as the Local adapter, select the Initiator IP in the same subnet as the IP address of the partner server from the previous step. Confirm the actions to complete the Target Portal discovery.



8. Now, all the target portals are added on the first node.




9. Repeat the steps 1-8 on the partner node.

Connecting Targets


1. Click the Targets tab. The previously created targets are listed in the Discovered Targets section.

NOTE: If the created targets are not listed, check the firewall settings of the StarWind Server as well as the list of networks served by the StarWind Server (go to StarWind


Management Console -> Configuration -> Network). Alternatively, check the Access Rights tab on the corresponding StarWind VSAN server in StarWind Management Console for any restrictions.




2. Select the Witness target from the local server and click Connect.
3. Enable checkboxes as shown in the image below. Click Advanced.



4. Select Microsoft iSCSI Initiator in the Local adapter dropdown menu. In the Initiator IP field, select the IP address for the iSCSI channel. In the Target portal IP, select the corresponding portal IP from the same subnet. Confirm the actions.



5. Repeat the steps 2-4 to connect to partner node.
6. Select the CSV1 target discovered from the local server and click Connect.
7. Enable checkboxes as shown in the image below. Click Advanced.




8. Select Microsoft iSCSI Initiator in the Local adapter dropdown menu. In Target portal IP, select 172.16.10.10. Confirm the actions.

9. Select the partner target from the other StarWind node and click Connect.

10. Repeat the step 6.

11. Select Microsoft iSCSI Initiator in the Local adapter dropdown menu. In the Initiator IP field, select the IP address for the iSCSI channel. In the Target portal IP, select the corresponding portal IP from the same subnet. Confirm the actions.



11. Repeat the steps 1-10 for all remaining HA device targets.

12. Repeat the steps 1-11 on the other StarWind node, specifying corresponding data channel IP addresses.


Configuring Multipath

NOTE: It is recommended to configure the different MPIO policies depending on iSCSI channel throughput. For 1 Gbps iSCSI channel throughput, it is recommended to set Failover Only or Least Queue Depth MPIO load balancing policy. For 10 Gbps iSCSI channel throughput, it is recommended to set Round Robin or Least Queue Depth MPIO

load balancing policy.

1. Configure the MPIO policy for each target with the load balance policy of choice. Select the Target located on the local server and click Devices.

2. In the Devices dialog, click MPIO.




3. Select the appropriate load balancing policy.


4. Repeat the steps 1-3 for configuring the MPIO policy for each remaining device on the current node and on the partner node.

Connecting Disks to Servers


1. Open the Disk Management snap-in. The StarWind disks will appear as unallocated and offline.




2. Bring the disks online by right-clicking on them and selecting the Online menu option.
3. Select the CSV disk (check the disk size to be sure) and right-click on it to initialize.
4. By default, the system will offer to initialize all non-initialized disks. Use the Select Disks area to choose the disks. Select GPT (GUID Partition Style) for the partition style to be applied to the disks. Press OK to confirm.



5. Right-click on the selected disk and choose New Simple Volume.
6. In New Simple Volume Wizard, indicate the volume size. Click Next.
7. Assign a drive letter to the disk. Click Next.




8. Select NTFS in the File System dropdown menu. Keep Allocation unit size as Default. Set the Volume Label of choice. Click Next.



9. Press Finish to complete.

10. Complete the steps 1-9 for the Witness disk. Do not assign any drive letter or drive path for it.



11. On the partner node, open the Disk Management snap-in. All StarWind disks will appear offline. If the status is different from the one shown below, click Action->Refresh in the top menu to update the information about the disks.

12. Repeat step 2 to bring all the remaining StarWind disks online.

Creating A Failover Cluster In Windows Server


NOTE: To avoid issues during the cluster validation configuration, it is recommended to install the latest Microsoft updates on each node.

NOTE: Server Manager can be opened on the server with desktop experience enabled (necessary features should be installed). Alternatively, the Failover cluster can be managed with Remote Server Administration Tools:


<https://docs.microsoft.com/en-us/windows-server/remote/remote-server-administration-tools>

NOTE: For converged deployment (SAN & NAS running as a dedicated storage cluster) the Microsoft Failover Cluster is deployed on separate computing nodes. Additionally, for the converged deployment scenario, the storage nodes that host StarWind SAN & NAS as CVM or bare metal do not require a domain controller and Failover Cluster to operate.


1. Open Server Manager. Select the Failover Cluster Manager item from the Tools menu.




2. Click the Create Cluster link in the Actions section of Failover Cluster Manager.



3. Specify the servers to be added to the cluster. Click Next to continue.




4. Validate the configuration by running the cluster validation tests: select Yes... and click Next to continue.




5. Specify the cluster name.

NOTE: If the cluster servers get IP addresses over DHCP, the cluster also gets its IP address over DHCP. If the IP addresses are set statically, set the cluster IP address manually.




6. Make sure that all settings are correct. Click Previous to make any changes or Next to proceed.




NOTE: If checkbox Add all eligible storage to the cluster is selected, the wizard will add all disks to the cluster automatically. The device with the smallest storage volume will be assigned as a Witness. It is recommended to uncheck this option before clicking Next and add cluster disks and the Witness drive manually.

7. The process of the cluster creation starts. Upon the completion, the system displays the summary with the detailed information. Click Finish to close the wizard.




Adding Storage to the Cluster


1. In Failover Cluster Manager, navigate to Cluster -> Storage -> Disks. Click Add Disk in the Actions panel, choose StarWind disks from the list and confirm the selection.




2. To configure the cluster witness disk, right-click on Cluster and proceed to More Actions -> Configure Cluster Quorum Settings.




3. Follow the wizard and use the Select the quorum witness option. Click Next.




4. Select Configure a disk witness. Click Next.




5. Select the Witness disk to be assigned as the cluster witness disk. Click Next and press Finish to complete the operation.




6. In Failover Cluster Manager, Right-click the disk and select Add to Cluster Shared Volumes.



7. If renaming of the cluster shared volume is required, right-click on the disk and select Properties. Type the new name for the disk and click Apply followed by OK.



8. Perform the steps 6-7 for any other disk in Failover Cluster Manager. The resulting list of disks will look similar to the screenshot below.




Configuring Cluster Network Preferences


1. In the Networks section of the Failover Cluster Manager, right-click on the network from the list. Set its new name if required to identify the network by its subnet. Apply the change and press OK.

NOTE: Please double-check that cluster communication is configured with redundant networks:


<https://docs.microsoft.com/en-us/windows-server/failover-clustering/smb-multichannel>



2. Rename other networks as described above, if required.



3. In the Actions tab, click Live Migration Settings. Uncheck the synchronization network, while the iSCSI network can be used if it is 10+ Gbps. Apply the changes and click OK.




The cluster configuration is completed and it is ready for virtual machines deployment. Select Roles and in the Action tab, click Virtual Machines -> New Virtual Machine. Complete the wizard.

Configuring File Shares


Please follow the steps below if file shares should be configured on cluster nodes.

Configuring The Scale-Out File Server Role


1. To configure the Scale-Out File Server Role, open Failover Cluster Manager.
2. Right-click the cluster name, then click Configure Role and click Next to continue.




3. Select the File Server item from the list in High Availability Wizard and click Next to continue.



4. Select Scale-Out File Server for application data and click Next.




5. On the Client Access Point page, in the Name text field, type the NetBIOS name that will be used to access a Scale-Out File Server.




Click Next to continue.


6. Check whether the specified information is correct. Click Next to continue or Previous to change the settings.




7. Once the installation is finished successfully, the Wizard should now look like the screenshot below.
Click Finish to close the Wizard.




8. The newly created role should now look like the screenshot below.




NOTE: If the role status is Failed and it is unable to Start, please, follow the next steps:



- open Active Directory Users and Computers
- enable the Advanced view if it is not enabled
- edit the properties of the OU containing the cluster computer object (in this case - Production)
- open the Security tab and click Advanced
- in the appeared window, press Add (the Permission Entry dialog box opens), click Select a principal
- in the appeared window, click Object Types, select Computers, and click OK
- enter the name of the cluster computer object (in this case - Production)



- go back to Permission Entry dialog, scroll down, and select Create Computer Objects,




- click OK on all opened windows to confirm the changes
- open Failover Cluster Manager, right-click SOFS role and click Start Role


Configuring File Share

To Add File Share:


- open Failover Cluster Manager
- expand the cluster and then click Roles
- right-click the file server role and then press Add File Share
- on the Select the profile for this share page, click SMB Share – Applications and then click Next




5. Select a CSV to host the share. Click Next to proceed.




6. Type in the file share name and click Next.



7. Make sure that the Enable Continuous Availability box is checked. Click Next to proceed.




8. Specify the access permissions for the file share.




NOTE:

- for the Scale-Out File Server for Hyper-V, all Hyper-V computer accounts, the SYSTEM account, and all Hyper-V administrators must be provided with the full control on the share and file system
- for the Scale-Out File Server on Microsoft SQL Server, the SQL Server service account must be granted full control on the share and the file system

9. Check whether specified settings are correct. Click Previous to make any changes or click Create to proceed.




10. Check the summary and click Close to close the Wizard.



To Manage Created File Shares:


- open Failover Cluster Manager
- expand the cluster and click Roles
- choose the file share role, select the Shares tab, right-click the created file share, and select Properties:




Configuring The File Server For General Use Role

NOTE: To configure File Server for General Use, the cluster should have available storage


1. To configure the File Server for General Use role, open Failover Cluster Manager.
2. Right-click on the cluster name, then click Configure Role and click Next to continue.




3. Select the File Server item from the list in High Availability Wizard and click Next to continue.



4. Select File Server for general use and click Next.




5. On the Client Access Point page, in the Name text field, type the NETBIOS name that will be used to access the File Server and IP for it.




Click Next to continue.

6. Select the Cluster disk and click Next.




7. Check whether the specified information is correct. Click Next to proceed or Previous to change the settings.




8. Once the installation has been finished successfully, the Wizard should now look like the screenshot below.

Click Finish to close the Wizard.




9. The newly created role should now look like the screenshot below.




NOTE: If the role status is Failed and it is unable to Start, please, follow the next steps:

- open Active Directory Users and Computers

- enable the Advanced view if it is not enabled
- edit the properties of the OU containing the cluster computer object (in this case - Production)
- open the Security tab and click Advanced
- in the appeared window, press Add (the Permission Entry dialog box opens), click Select a principal
- in the appeared window, click Object Types, select Computers, and click OK
- enter the name of the cluster computer object (in this case - Production)



- go back to Permission Entry dialog, scroll down, and select Create Computer Objects




- click OK on all opened windows to confirm the changes

- open Failover Cluster Manager, right-click File Share role and click Start Role


Configuring Smb File Share

To Add SMB File Share


1. Open Failover Cluster Manager.
2. Expand the cluster and then click Roles.
3. Right-click the File Server role and then press Add File Share.
4. On the Select the profile for this share page, click SMB Share - Quick and then click Next.



5. Select available storage to host the share. Click Next to continue.




6. Type in the file share name and click Next.




7. Make sure that the Enable Continuous Availability box is checked. Click Next to


continue.




8. Specify the access permissions for the file share.



9. Check whether specified settings are correct. Click Previous to make any changes or Next/Create to continue.



10. Check the summary and click Close.




To manage created SMB File Shares

11. Open Failover Cluster Manager.

12. Expand the cluster and click Roles.


13. Choose the File Share role, select the Shares tab, right-click the created file share, and select Properties.




Configuring Nfs File Share

To Add NFS File Share


1. Open Failover Cluster Manager.
2. Expand the cluster and then click Roles.
3. Right-click the File Server role and then press Add File Share.
4. On the Select the profile for this share page, click NFS Share - Quick and then click Next.



5. Select available storage to host the share. Click Next to continue.




6. Type in the file share name and click Next.





7. Specify the Authentication. Click Next and confirm the message in pop-up window to

continue.




8. Click Add and specify Share Permissions.







9. Specify the access permissions for the file share.



10. Check whether specified settings are correct. Click Previous to make any changes or click Create to continue.




11. Check a summary and click Close to close the Wizard.



To manage created NFS File Shares:








- open Failover Cluster Manager
- expand the cluster and click Roles
- choose the File Share role, select the Shares tab, right-click the created file share, and select Properties



Conclusion

Following this guide, IT professionals will get a successful cluster deployment on Microsoft Windows Server with a shared highly-available storage, provided by StarWind VSAN CVM.

Contacts

US Headquarters	EMEA and APAC
 +1 617 829 44 95	 +44 2037 691 857 (United Kingdom)
 +1 617 507 58 45	 +49 800 100 68 26 (Germany)
 +1 866 790 26 46	 +34 629 03 07 17 (Spain and Portugal)
	 +33 788 60 30 06 (France)

Customer Support Portal: <https://www.starwind.com/support>

Support Forum: <https://www.starwind.com/forums>

Sales: sales@starwind.com

General Information: info@starwind.com



StarWind Software, Inc. 100 Cummings Center Suite 224-C Beverly MA 01915, USA
www.starwind.com ©2024, StarWind Software Inc. All rights reserved.