

StarWind Virtual SAN®

ODX (Off-loaded Data Transfer)
Configuration and Performance
Tuning Guide

FEBRUARY 2018









Trademarks

"StarWind", "StarWind Software" and the StarWind and the StarWind Software logos are registered trademarks of StarWind Software. "StarWind LSFS" is a trademark of StarWind Software which may be registered in some jurisdictions. All other trademarks are owned by their respective owners.

Changes

The material in this document is for information only and is subject to change without notice. While reasonable efforts have been made in the preparation of this document to assure its accuracy, StarWind Software assumes no liability resulting from errors or omissions in this document, or from the use of the information contained herein. StarWind Software reserves the right to make changes in the product design without reservation and without notification to its users.

Technical Support and Services

If you have questions about installing or using this software, check this and other documents first - you will find answers to most of your questions on the <u>Technical Papers</u> webpage or in <u>StarWind Forum</u>. If you need further assistance, please <u>contact us</u>.

About StarWind

StarWind is a pioneer in virtualization and a company that participated in the development of this technology from its earliest days. Now the company is among the leading vendors of software and hardware hyper-converged solutions. The company's core product is the years-proven StarWind Virtual SAN, which allows SMB and ROBO to benefit from cost-efficient hyperconverged IT infrastructure. Having earned a reputation of reliability, StarWind created a hardware product line and is actively tapping into hyperconverged and storage appliances market. In 2016, Gartner named StarWind "Cool Vendor for Compute Platforms" following the success and popularity of StarWind HyperConverged Appliance. StarWind partners with world-known companies: Microsoft, VMware, Veeam, Intel, Dell, Mellanox, Citrix, Western Digital, etc.

Copyright ©2009-2018 StarWind Software Inc.

No part of this publication may be reproduced, stored in a retrieval system, or transmitted in any form or by any means, electronic, mechanical, photocopying, recording or otherwise, without the prior written consent of StarWind Software.


Contents

Introduction	∠
Enabling ODX support inside StarWind VSAN	
Checking the ODX proper functioning	[
Summary	1(

Introduction

This document is intended for experienced StarWind users and Microsoft administrators, who want to decrease the network workload by using Offloaded Data Transfers (ODX). The guide describes how to check ODX proper functioning and its productivity.

ODX is a feature that allows speeding up certain "copy and move" operations by allowing them to be performed on the storage, instead of running them between the client and storage through the network. The servers only exchange the corresponding commands and service info, while data transferring is performed on the storage layer. As a result, the creation and copying of data takes less time without overloading the channel. ODX is supported on Windows 8/2012 and later versions.



A full set of up-to-date technical documentation can always be found <u>here</u>, or by pressing the **Help** button in the StarWind Management Console.

For any technical inquiries please visit our <u>online community</u>, <u>Frequently Asked Questions</u> page, or use the <u>support form</u> to contact our technical support department.

Enabling ODX support inside StarWind VSAN

By default, ODX is turned off in StarWind configuration file. To turn on the ODX support we need to modify StarWind configuration file by following the steps below.


NOTE: StarWind service must be stopped before editing the configuration file.

- 1. Stop StarWind service.
- 2. Navigate to StarWind root directory and locate the StarWind.cfg file.


 The default location is "C:\Program Files\StarWind Software\StarWind\StarWind.cfg".
- 3. Make a backup of the StarWind.cfg file.
- 4. Open the file with text editor, find the ODX string **<OdxEnabled value="no"/>** under the **<hardwareacceleration>** section and change "no" to "yes". Finally, the string must be like **<OdxEnabled value="yes"/>**.
- 5. Save the changes and close the text editor.
- 6. Restart the host where StarWind VSAN is installed.

Checking the ODX proper functioning


7. Create the device in <u>StarWind Management Console</u>.



8. Connect the device on the client through iSCSI Initiator



9. Initialize and format the disk using Disk Management.



10. ODX support settings can be changed by editing the registry key. It can be done via PowerShell using the commands below.

To turn on the ODX support on Microsoft level, use the command:

```
\label{lem:control}  \begin{tabular}{ll} SYSTEM $$ \control{FileSystem -Name "FilterSupportedFeaturesMode" -Value 0 } \end{tabular}
```

To turn off the ODX support, run the command:

```
Set-ItemProperty HKLM:\SYSTEM\CurrentControlSet\Control\FileSystem -Name
"FilterSupportedFeaturesMode" -Value 1
```

This part further describes how to check ODX functioning, by comparing the speed of the .vhdx file creation in two ways: ODX support is enabled in the StarWind configuration file and disabled / enabled on the Windows level.

11. Turn off the ODX support on the Microsoft level:

The .vhdx file can be created on the disk (in this case, disk O:) using GUI. Alternatively, it can be done via PowerShell.

Creation:

```
Measure-Command { New-VHD -Path E:\TestVHD-15GB.vhdx -Size 15GB -Fixed}
```

Copying:

```
Measure-Command { Copy-Item E:\TestVHD-15GB.vhdx E:\CopiedTestVHD.vhdx}
```

The workload on the network between the client and the server is the main parameter for checking the ODX functioning.

Without the ODX it took around 1 minute and 7 seconds to create the test .vhdx file.


```
Administrator: Windows PowerShell

PS C:\Windows\system32> Measure-Command { New-VHD -Path 0:\TestVHD-15GB.vhdx -Size 15GB -Fixed}

Days : 0
Hours : 0
Minutes : 1
Seconds : 7
Milliseconds : 215
Ticks : 672155051
TotalDays : 0.0007779572334953704
TotalDays : 0.0186709736388899
TotalMinutes : 1.12025841833333
TotalSeconds : 67.2155051
TotalMilliseconds : 67.2155051

PS C:\Windows\system32> ___
```

The workload during the creation process was significant:




12. With ODX support enabled on Microsoft level, the time for .vhdx file creation is 47 seconds:

```
Administrator: Windows PowerShell

PS C:\Windows\system32> Set-ItemProperty HKLM:\SYSTEM\CurrentControlSet\Control\FileSystem -Name "FilterSupportedFeature of Sciwindows\system32> Measure-Command { New-VHD -Path 0:\TestVHD-15GB.vhdx -Size 15GB -Fixed}

Days : 0
Hours : 0
Minutes : 0
Seconds : 42
Milliseconds : 316
Ticks : 423166997
TotalDays : 0.0017546388055556
TotalHours : 0.0117546388055556
TotalHours : 0.012783283333333
TotalSeconds : 42.3166997
TotalMilliseconds : 42.3166997
TotalMilliseconds : 42.3166997
```

The network workload is minimized, since only a small amount of data is transferred:



Copying files or VMs between server storages may be also used for testing ODX. In case there is a cluster, it is possible to create, copy, and move files between CSV volumes or migrate VMs.

Summary

ODX support allows StarWind to offload multiple storage operations from the Hyper-V hosts to the storage array itself. Thus, these operations are carried out much faster and with no impact on the hypervisor's performance.

Contacts

US Headquarters	EMEA and APAC
1-617-449-77 17	+44 203 769 18 57 (UK)
1-617-507-58 45	+34 629 03 07 17
1-866-790-26 46	(Spain and Portugal)

Customer Support Portal: https://www.starwind.com/support

Support Forum: https://www.starwind.com/forums

Sales: <u>sales@starwind.com</u>

General Information: info@starwind.com



StarWind Software, Inc. 35 Village Rd., Suite 100, Middleton, MA 01949 USA <u>www.starwind.com</u> ©2018, StarWind Software Inc. All rights reserved.